

Mitcorp



VideoscopeX

VIDEOSCOPE UTILITY APPLICATION



USER MANUAL



VideoscopeX UI & Functions

1. Download & Connection

Download and install the APP from Google play/APP Store. Then connect to X3000 via Wi-Fi.(You can find the setting in X3000 MANUAL-[2.2.3] section)

Android (5 functions)	Apple-iOS (4 functions)
	

Note: When the APP is installed, a “VideoscopeX” folder will be created in mobile album list. You can find the images via the original mobile album list.


Individual function instructions are break down into next sections[2]~[5].

2. Stream




Press the **Stream** button to enter this mode. In this mode, your mobile device can sync to X3000's monitor real time display (just share image). You cannot control any function of the system.

3. Remote




Press the **Remote** button to enter this mode. In this mode, your mobile device can sync to X3000's monitor real time display and press any button on screen.


4. View and Import / Import




Press the **View and Import** button to enter this mode.



You can change the browser type depending on OS.




Select & save images from X3000 into mobile device.



Press save button and check the album on mobile device.

*** On the iOS version:**


Select images by check box, then save those files into the "Files APP" directly or create new folder by your own management requirement.




5. Report




Press the **Report** button to enter this mode.




Add image from camera or album



Make notes by columns for each image. Choose print format.



After editing, tap "Preview" to check the report or tap "SavePDF" to save file




Preview mode. You can save the file on device or google drive as common procedure.




PDF file will also be saved in the "VideoscopeX" folder.

* Report, View & Share (iOS version):

Select images by check box, then save those files into the "Files APP" directly or create new folder by your own management requirement.



6. View and Share (Android)



In Android platform, the view and share of the PDF report file is an independent function.

Press the **View and Share** button to enter this mode. The interface will show saved file list. Short tap any file to open and read PDF file. Long press any file into check box, then share the files as common file sharing procedure.

Mitcorp

NOV.2025